Subject: Default value - changing when inserting new record
Posted by htManager on Wed, 05 Feb 2025 10:05:22 GMT
View Forum Message <> Reply to Message

Hi Tony,

I have a field with type tinyint(1) and default value "1". In some cases I want to change the value to â€œ0â€•, when inserting a new record. But this change is not accepted.
I tried it analogously to the "UML diagram for Add 1" in the functions _cm_pre_InsertRecord(), _cm_post_InsertRecord() and in _cm_formatData() but in the end the value '1' is always entered.
I have currently deleted the default value and am checking in _cm_post_InsertRecord() which value I need to enter.
Is this behavior desired by the framework? Or in which function do I have to change the default value?

Subject: Re: Default value - changing when inserting new record
Posted by AJM on Thu, 06 Feb 2025 11:35:36 GMT
View Forum Message <> Reply to Message

I have managed to replicate this issue and found the offending code. In file std.table.class.inc you will see lines 6890 and 6891 as follows:

} elseif (empty($insertarray[$field]) AND !empty($spec['default'])) {
 Â Â Â $insertarray[$field] = $spec['default'];

If you either remove these lines or comment them out your problem should disappear.

Subject: Re: Default value - changing when inserting new record
Posted by htManager on Thu, 06 Feb 2025 12:29:57 GMT
View Forum Message <> Reply to Message

Thank you very much. I will do this.